



# VPN Client

6.8 or higher

for Windows

User Guide

## Contents

- [Introduction](#) on page 2
- [Installing and upgrading](#) on page 2
- [Using the right-click menu](#) on page 3
- [Connecting to a new gateway](#) on page 5
- [Connecting and authenticating](#) on page 10
- [Managing certificates](#) on page 13
- [Monitoring VPN connections](#) on page 19
- [Change Forcepoint VPN Client settings](#) on page 21
- [Close the VPN connection](#) on page 24
- [Disable the Forcepoint VPN Client](#) on page 24
- [Troubleshooting VPN connections](#) on page 25

# Introduction

This guide provides end-user instructions for installing and using Forcepoint VPN Client.

Forcepoint VPN Client is a software application that runs on your computer. The client allows you to connect to your organization's network from anywhere. Using a virtual private network (VPN) establishes a secure, encrypted connection that protects the information you transfer through the VPN gateway on Forcepoint Next Generation Firewall (Forcepoint NGFW). Your administrator defines which networks are protected by the VPN tunnel.

# Installing and upgrading

The Forcepoint VPN Client can be added as a new installation or as an upgrade.

## Install the Forcepoint VPN Client

Your administrator provides the installation file.

### Before you begin

Check with your administrator about the installation process. Your administrator might be using a standard installation file or a preconfigured file.

## Steps

- 1) Double-click the installation executable file.  
The **Forcepoint VPN Client Setup** window opens.
- 2) Click **Install**.
- 3) Click **Next**, then follow the on-screen prompts.



### Note

You might see one or more confirmation requests during the installation. Allow the installation of all drivers and components.

## Next steps

When the installation is complete, connect to a new gateway to start using the Forcepoint VPN Client.

### Related tasks

[Connecting to a new gateway](#) on page 5

# Upgrade the Forcepoint VPN Client

When there is a new version of the Forcepoint VPN Client, you can upgrade the existing installation.

## Steps


- 1) Double-click the executable file.  
A confirmation message appears.
- 2) Click **Yes**.  
The **Welcome** screen for the installation wizard opens.
- 3) Click **Next** to start the upgrade.
- 4) Accept the License Agreement and click **Next** to continue.
- 5) When the upgrade is finished, click **Finish** to close the wizard.

# Using the right-click menu

You have access to several commands and properties in the right-click menu of the Forcepoint VPN Client icon. The color of the Forcepoint VPN Client icon changes according to the status of the Forcepoint VPN Client. The available menu commands change with the status of the VPN connection.

**Tip**

View the status as text by holding the cursor over the Forcepoint VPN Client icon in the system tray on the Windows taskbar.

**Forcepoint VPN Client right-click menu options**

Option	Definition
<b>Properties</b>	More actions and status information.
<b>Connect to New Gateway</b>	Adds a gateway.
<b>Select Gateway</b>	Select where you want to connect.
<b>Connect</b>	Use <b>Connect/Disconnect</b> to open and close a VPN.
<b>Connect to End-Point</b>	Select endpoint if the gateway has several endpoints.
<b>Reauthenticate</b>	Reauthenticate when convenient (instead of waiting for the authentication timeout).
<b>Disable VPN</b>	Disconnect the VPN and turn off the automatic VPN connection trigger.
<b>Exit</b>	Exit the Forcepoint VPN Client.

More information and commands are available in the **Forcepoint VPN Client Properties** dialog box that opens through the right-click menu or by double-clicking the Forcepoint VPN Client icon.

**Related concepts**

[Monitoring VPN connections](#) on page 19

# Connecting to a new gateway

Forcepoint VPN Client connects to a *gateway*, a device within your organization's network that is integrated with the rest of the network. Connecting to a gateway for the first time requires a different process than later connections.

## Before you begin

If the gateway requires certificate authentication, you cannot connect to the gateway until you have a valid certificate. Your administrator tells you if you must obtain a certificate.

The VPN connection requires identity verification in two directions, known as *mutual authentication*.

- Certificate fingerprint — The first time the Forcepoint VPN Client connects to a gateway, the identity of the gateway is verified to the Forcepoint VPN Client with the certificate fingerprint.
- User authentication — User identity is authenticated each time you connect to a gateway.



### Note

Your administrator tells you what to use in your environment.

After the installation, you cannot connect to gateways and endpoints until they are configured in the Forcepoint VPN Client. The administrator might have preconfigured the gateways for you so that you can connect to them by selecting them in a list. Alternatively, you can get the gateway configuration from the administrator as a file that has been added to the installation. The gateways are included in the client when you start using it. The administrator can also tell you which IP address of gateway you should use. You can then add the gateway manually in the VPN Client. If the Forcepoint VPN Client is configured to allow domain logon through the Windows logon screen, only gateways that you have connected to at least once are available.



### Note

Domain logon is only supported for IPsec VPN connections. You cannot use domain logon with SSL VPN connections.

## Related tasks

- [Check the list of available gateways](#) on page 5
- [Connect to a preconfigured gateway](#) on page 6
- [Add a gateway manually](#) on page 7
- [Managing certificates](#) on page 13

# Check the list of available gateways

View the gateways that are already configured.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.

- 2) Click the **Gateways** tab. All configured gateways are listed in the table.

### Related tasks

- [Connect to a preconfigured gateway on page 6](#)
- [Select the authentication method on page 12](#)

## Connect to a preconfigured gateway

The administrator might have configured a gateway for you in the installation package.



### Note

The administrator tells you if you need a certificate. If the gateway requires certificate authentication, you must have a valid certificate to connect to the gateway.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select an item from the menu.
  - No preconfigured gateways yet — Select **Connect to New Gateway** directly at the main level.
  - Preconfigured gateway available — Select **Select Gateway > Connect to New Gateway**.

- 2) Make sure that **Preconfigured Gateway** is selected.



### Note

If the setting is disabled, add any new gateways manually.

- 3) Select the preconfigured gateway.
- 4) (Optional) Select the endpoint to connect to.



### Tip

Endpoints usually correspond to different Internet connections at the office.

- 5) Select whether authentication is based on a manually entered user name and password or on the user certificate.

Your administrator tells you what to select.

- 6) For IPsec VPN connections, click **Advanced** to define the settings.



#### Note

Do not change the Advanced settings unless your network administrator specifically instructs you to.

Option	Definition
<b>Trust CAs in Microsoft Certificate Store</b>	Select this option to use the Microsoft Certificate Store on the client computer. The certificate sent by the VPN gateway is verified against the certificate authority (CA) certificates in the Microsoft Certificate Store.  The client connects to the VPN gateway only if a matching certificate is found in the store.
<b>Gateway Authentication</b> (User Name Authentication only)	Select the signature type that matches the gateway certificate.

- 7) Click **OK**. The **User Authentication** dialog box opens.

## Next steps

Check the gateway certificate fingerprint.

### Related tasks

[Check the gateway certificate fingerprint](#) on page 9

# Add a gateway manually

If you have not previously connected to the gateway and it has not been preconfigured for you, you can add it manually.

## Before you begin

To manually connect to a gateway, you need the following information from your network administrator:

- An address for each gateway that you connect to
- Information about which credentials to use for authentication
- The gateway certificate fingerprint that allows you to verify the gateway identity
- A valid certificate to connect to the gateway. The administrator provides the certificate if certificate authentication is required.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select an item from the menu.

- No preconfigured gateways yet — Select **Connect to New Gateway** directly at the main level.
  - Preconfigured gateway available — Select **Select Gateway > Connect to New Gateway**.
- 2) Select **New Gateway**.  
If there are no preconfigured gateways that have not been contacted, the new gateway setting is selected by default.
  - 3) In the **Protocol** field, select **IPsec** or **SSL**. Your administrator tells you what to select.
  - 4) In the **Host Name** field, enter the gateway address.  
Your administrator tells you what to select.
  - 5) For SSL VPN connections, click **SSL Port** and enter the port number.  
Your administrator tells you what to select.
  - 6) In the Authentication section, select whether authentication is based on a manually entered user name and password or on the user certificate.  
Your administrator tells you what to select.
  - 7) For IPsec VPN connections, click **Advanced** to define the settings.

**Note**

Do not change the Advanced settings unless your network administrator specifically instructs you to.

Option	Definition
<b>Trust CAs in Microsoft Certificate Store</b>	Select this option to use the Microsoft Certificate Store on the client computer. The certificate sent by the VPN gateway is verified against the certificate authority (CA) certificates in the Microsoft Certificate Store.  The client connects to the VPN gateway only if a matching certificate is found in the store.
<b>Gateway Authentication</b> (User Name Authentication only)	Select the signature type that matches the gateway certificate.

- 8) Click **OK**.
- 9) For certificate authentication, enter the passphrase defined for the certificate. The **New Gateway** dialog box opens. You are prompted to verify the identity of the gateway by checking its certificate fingerprint.

## Next steps

Check the gateway certificate fingerprint.



**Related tasks**[Managing certificates](#) on page 13

## Check the gateway certificate fingerprint

When you connect to a new gateway for the first time, you must verify its identity.


The certificate fingerprint is an important security feature that ensures confidential communication. A fingerprint that does not match might indicate a malicious attempt to spy on your communications.

**Note**

If the gateway certificate changes, you might have to recheck the certificate fingerprint. If a recheck is necessary, your administrator informs you and provides you with the information for checking the new certificate fingerprint.

### Steps

- 1) Check the entries in the **Subject Name** and the **Certificate Fingerprint** fields against the information the administrator has provided.



- 2) Proceed according to the result of the comparison:
  - Values do not match — Click **Cancel** and contact the administrator.
  - Values match — Click **OK**.

**Related tasks**[Select the authentication method](#) on page 12

# Connecting and authenticating

There are several ways to establish a VPN connection and authenticate to a gateway.

Connection methods include the following:

- Domain logon — You might be able to log on to the VPN on the Windows logon screen. This way, the computer can connect all internal network resources, such as network drives, immediately when it starts.



## Note

Domain logon is only supported for IPsec VPN connections. You cannot use domain logon with SSL VPN connections.

- Manual connection — You can manually connect your Forcepoint VPN Client to a gateway.
- Change endpoint — You can select which endpoint connection the gateway uses.

However you connect, when you are outside the office, the Forcepoint VPN Client automatically prompts you to authenticate when you access a service or application that requires a VPN. You can authenticate yourself with either user name and password, a certificate, or a smart card. Usually, the administrator selects a single method that you can use. In some cases, you can select from alternative methods. As a further security measure, your authentication is valid for a specific period; after that, you must reauthenticate. Reauthentication might also be required if the VPN connection is lost due to network problems.

## Connect to a gateway from a Windows logon

If domain logon is enabled, you can open the VPN connection at the Windows logon screen.



## Note

Domain logon is only supported for IPsec VPN connections. You cannot use domain logon with SSL VPN connections.

Using the domain logon gives you automatic connections to network drives and other resources in your organization. The domain logon is helpful to avoid error messages and delays that can sometimes occur if resources are not available.

- You can use the logon screen to access gateways that you have used previously.

## Steps

- 1) On the Windows logon screen, select **Switch User**.  
Icons are displayed for all configured user accounts and previously contacted VPN gateways.
- 2) Select the gateway that you want to connect to.  
The logon screen for that gateway is displayed.
  - If you do not see any VPN gateways even though you have successfully connected to a gateway previously, this feature is most likely deactivated in your installation.
  - If a VPN connection is already active, you can deactivate it here.
- 3) For user name and password authentication, make a selection for the **Use same credentials to log on to** setting:
  - Credentials valid for both Windows and Forcepoint VPN Client — Select the option.

- Different credentials — Deselect the option to avoid a Windows logon failure.
- 4) Enter your credentials for the VPN connection.  
The VPN is established.  
Depending on the authentication method and the options selected, you either need to log on to Windows or you are automatically logged in.

## Result

After logging on to Windows, the VPN connection is active. After the Windows desktop loads, you can use resources through the VPN.

### Related concepts

[Monitoring VPN connections on page 19](#)

### Related tasks

[Connecting to a new gateway on page 5](#)

[Select the authentication method on page 12](#)

[Activate or deactivate domain logon on page 22](#)

[Close the VPN connection on page 24](#)

## Connect to a gateway manually

You can select the gateway that the Forcepoint VPN Client connects to.

- Connect to a gateway that is not listed — If you want to connect to a gateway that is not yet listed, you must add the gateway.
- Connect to the gateway the Forcepoint VPN Client contacted — From the Forcepoint VPN Client right-click menu, select **Connect** and enter your credentials.
- Connect to a different gateway than the last gateway used — From the Forcepoint VPN Client right-click menu, select **Select Gateway** and then select the gateway from the submenu. Enter your credentials to connect. The gateway is stored as your default connection.

### Related tasks

[Connecting to a new gateway on page 5](#)

[Select the authentication method on page 12](#)

[Add a gateway manually on page 7](#)

## Connect using an alternative endpoint

Some gateways can be reached through several endpoints. These endpoints usually correspond to different Internet connections at the office you are connecting to.

Selecting a different endpoint might be useful when one of the Internet connections at the office you are connecting to is experiencing technical difficulties.



#### Note

If the endpoint connection becomes unavailable, another endpoint will be automatically selected if two or more endpoints have been defined for the gateway.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, select **Connect to End-Point**, then select the endpoint.
- 2) Enter your credentials for the VPN connection.  
The VPN is established and the endpoint you selected is stored as your default connection.

## Select the authentication method

A gateway might allow you to select how you want to authenticate.

If you authenticate to a gateway with a user name and a password, the Forcepoint VPN Client prompts you to reauthenticate periodically. If a certificate or a smart card is used, reauthentication is automatic.



#### Note


All gateways might not accept all authentication methods.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Gateways** tab. All configured gateways are listed in the table.

- 3) Right-click the gateway for which you want to select the authentication method and select **Authentication > Username** or **Authentication > Certificate** | <name used in certificate>.

#### Authentication methods

Method	Explanation
User name and password	<p>The user name and password authentication dialog box appears for any method that requires you to enter your user name manually.</p> <p>The password you enter can be fixed or, for example, a code generated by a physical security token that you carry with you. The network administrator provides you the necessary details for logging on.</p> <div style="border: 1px solid #ccc; background-color: #f9f9f9; padding: 5px; margin-top: 10px;"> <p> <b>Note</b></p> <p>You cannot change your password through the Forcepoint VPN Client. Contact the network administrator if you need information for changing the password.</p> </div>
Certificate	<p>Certificates electronically identify a user or device, proving that they are who or what they claim to be. This verification is completed using public/private key pairs and digital signatures. A CA grants and verifies digital certificates.</p> <p>The certificate is protected with a passphrase that you or your administrator defined.</p> <p>If you have certificates that can be used for authentication in the Microsoft Certificates Store on your local computer, those certificates are also listed.</p>
Smart card	<p>If you have a smart card, the Forcepoint VPN Client uses the smart card software installed on your computer to prompt you for your passphrase when authentication is needed.</p> <p>The dialog box you see depends on the smart card software installed on your computer. The certificates stored on smart cards are included on the list of available certificates when you select the method for authenticating to a gateway.</p>

## Result

The selected authentication method is used the next time you authenticate yourself.

# Managing certificates

If you use certificates imported through the Forcepoint VPN Client, you can manage the imported certificates directly in the Forcepoint VPN Client.

- The signed certificates that you have imported are listed on the **Certificates** tab.
- Certificates stored on smart cards or in the Microsoft Certificates Store on the local computer are not listed on the **Certificates** tab. They are included on the list of available certificates when you select the authentication method for connecting to a gateway. You cannot otherwise manage these certificates in the Forcepoint VPN Client.

#### Related tasks

Select the authentication method on page 12

# Use internal certificates

---

The administrator might require that VPN connections use a client certificate.

There are two stages to the internal certificate process. You create a certificate request and send it to your network administrator to be signed. After being signed by the CA, the certificate must be imported into the Forcepoint VPN Client.

If the client certificate on your computer or the CA that signed the client certificate has expired, repeat the same process to renew the certificate.

## Create a basic certificate request

---


You can create a basic certificate request for an internal certificate in the Forcepoint VPN Client.

### Steps

- 1) Start the **Certificate Request Wizard**.
    - a) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
    - b) Click the **Certificates** tab.
    - c) Click **Create Certificate Request**.
  - 2) Verify that **Basic Mode** is selected and click **Next**.
  - 3) In the **User Name** field, enter the user name.

The user name must correspond to what is defined on the gateway.
  - 4) In the **Passphrase** field, enter and confirm a passphrase to use whenever you authenticate yourself using the certificate.

You can select this passphrase yourself. We recommend choosing a passphrase that meets the following requirements:

    - Be at least eight characters long
    - Contain a combination of numbers, letters, and special characters
- 
- Note**
- Secure passphrases are never based on personal information such as names, birthdays, ID numbers, or phone numbers.
- 5) Click **Create**. You are prompted to save the certificate request.
  - 6) Click **Save**. A file save dialog box opens.
  - 7) Save and send the file for signing.
    - a) Browse to the correct folder, enter a file name, and click **Save**. Make sure that **Certificate Requests (\*.csr)** is selected as the file type.

- b) (Optional) Click **Launch Default Windows E-Mail Application** to create a message in your default email application.
        - c) If you are not the administrator, send the certificate request .csr file that you saved to the administrator for signing.
- 8) Click **Finish** to close the wizard.

## Next steps

When you receive the signed internal certificate, import it.

# Import a signed certificate

---

A signed certificate must be imported into the Forcepoint VPN Client.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Certificates** tab.
- 3) Click **Import Certificate**.
- 4) Verify that **Internal Certificate** is selected and click **Next**.
- 5) Click **Select**.  
A Windows file browser opens.
- 6) Browse to the correct folder, select the signed certificate, and click **Open**.
- 7) Click **Finish** to close the wizard.

## Result

The certificate is now listed on the **Certificates** tab. The **Certificates** tab displays, among other information, the expiration date of the certificate.

# Use external certificates

---

There are three ways to use previously generated external certificates with the Forcepoint VPN Client.

You can use:

- An external certificate stored on a smart card
- A certificate stored in the Microsoft Certificates Store on your local computer
- An imported certificate in the Forcepoint VPN Client

You can either import the external certificate and its private key as a single PKCS # 12 file or as two separate files. Follow the instructions if the administrator tells you that you must import an external certificate in the Forcepoint VPN Client.


## Import a PKCS #12 file

Import the file containing the certificate and the private key.

### Steps

- 1) Open the **Import Certificate Wizard**.
    - a) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
    - b) Click the **Certificates** tab.
    - c) Click **Import Certificate**.
  - 2) Select **External Certificate**.
  - 3) Select **PKCS # 12 File** and click **Next**.
  - 4) Click **Browse** and select the PKCS #12 file to import.
  - 5) In the **PKCS #12 Password** field, enter the PKCS #12 password for the certificate file.
  - 6) In the **Passphrase** field, enter and confirm a passphrase to use whenever you authenticate yourself using the certificate.

You can select this passphrase yourself. We recommend choosing a passphrase that meets the following requirements:

    - Be at least eight characters long
    - Contain a combination of numbers, letters, and special characters
- 
- Note**
- Secure passphrases are never based on personal information such as names, birthdays, ID numbers, or phone numbers.
- 7) Click **Next > Finish**.

### Result

The signed certificate is now listed on the **Certificates** tab. The **Certificates** tab displays, among other information, the expiration date of the certificate.



# Import separate certificate and private key files

If there is an existing external certificate and private key files that you want to use for authentication, you can import them into the Forcepoint VPN Client.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Certificates** tab.
- 3) Click **Import Certificate**. The **Import Certificate Wizard** opens.
- 4) Select **External Certificate**.
- 5) Select **Separate Certificate and Private Key Files** and click **Next**.
- 6) Click **Browse** to select the certificate file and private key file to import.
- 7) Click **Next > Finish**.

## Result

The certificate is now listed on the **Certificates** tab. The **Certificates** tab displays, among other information, the expiration date of the certificate.

# Change the certificate passphrase

You must enter a passphrase every time the Forcepoint VPN Client asks you to authenticate yourself using this certificate. You can change the passphrase of a certificate that you have imported through the Forcepoint VPN Client.

You can choose this passphrase yourself. We recommend choosing a passphrase that meets the following requirements:

- It is at least eight characters long.
- It contains a combination of numbers, letters, and special characters.



### Note

Secure passphrases are never based on personal information such as names, birthdays, ID numbers, or phone numbers.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Certificates** tab.

- 3) Right-click the certificate and select **Change Key Passphrase**.
- 4) Enter the current passphrase and the new passphrase in both fields provided, and click **OK**.

**Note**

If you leave the new passphrase fields empty, the private key of the certificate is not encrypted. For security reasons, it is highly recommended that you enter a passphrase.

## View user certificate details

To learn more about a user certificate, you can access the Microsoft Certificates Store on your computer and the issuer certificate in the Trusted Root Certification Store.

Although the **Windows Certificate** dialog box provides tools for installing the user certificate, installing the user certificate is not necessary for the operation of the Forcepoint VPN Client.

**Note**

This operating system dialog box is not part of the Forcepoint VPN Client. If you want more instructions for it, press **F1** to view the context-specific Windows help for this dialog box.

The **General**, **Details**, and **Certification Path** tabs provide detailed information about the certificate.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Certificates** tab.
- 3) Right-click the certificate and select **Details of User Certificate** or **Details of Issuer Certificate**. The **Windows Certificate** dialog box opens.

## Change the certificate user ID type

Several user IDs can be available for each imported certificate. The options available depend on which types of information are included in the certificate.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Certificates** tab.
- 3) Right-click the certificate that you want to change and select one of these options:
  - **Certificate ID to Use > E-mail**
  - **Certificate ID to Use > Subject Name**

- **Certificate ID to Use > DNS Name**
- **Certificate ID to Use > IP Address.**

## Delete certificates

---

Sometimes, an imported certificate might become unnecessary. In such cases, you can delete the obsolete certificate through the Forcepoint VPN Client.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Certificates** tab.
- 3) Right-click the certificate and select **Delete Certificate**.  
A confirmation dialog box appears.
- 4) Click **Yes** to permanently delete the certificate.

## Monitoring VPN connections

---





You can manage and monitor active VPN connections.


### VPN connection status

---


The color of the Forcepoint VPN Client icon shows the connection status. More details are available in the **Forcepoint VPN Client Properties** dialog box.

#### Forcepoint VPN Client status icons

Icon	Status
	VPN is disabled
	No VPN connection
	VPN established
	Connectivity problems

Icon	Status
	VPN error

You can manage and monitor the VPN connections on the **Status** tab of the Forcepoint VPN Client.



- 1 Progress of establishing a VPN connection.
- 2 Name of the currently selected gateway.
- 3 Status information.
- 4 Reauthentication is required at regular intervals. The timer shows how long it takes until the authentication dialog box automatically opens again.
- 5 Details of the active VPN connection.

## View active VPN connection details

Detailed information on the established VPN connection is available. This information is useful for advanced users and administrators. Interpreting the details requires knowledge about IPsec standards.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Status** tab.
- 3) Click **Details**. The **VPN Details** dialog box opens.

- 4) Check the settings used in the currently active VPN connection.  
IPsec-related terms are used as follows:
  - **IKE** — Settings for negotiation phase 1
  - **IPsec** — Settings for negotiation phase 2
- 5) Click **Close** when you are finished.

## View the configuration downloaded from a gateway

---

When you connect to a gateway, the Forcepoint VPN Client checks if there are previously downloaded settings from the gateway in question, and whether such settings are up to date. If necessary, a new configuration is downloaded, replacing the old configuration.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Gateways** tab.
- 3) Right-click a gateway to which you have previously connected and select **View Gateway Configuration**. The settings that the client has downloaded from that gateway are displayed in a new dialog box.
- 4) Click **Close** when you are finished.

## Change Forcepoint VPN Client settings

---

Your administrator might advise you to make some changes to your Forcepoint VPN Client to improve performance.

## Activate or deactivate user name memory

---

By default, the Forcepoint VPN Client remembers up to five most recently used user names. These stored user names prevent the need to type frequently used user names each time you authenticate.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Advanced** tab.

- 3) Select or deselect **Remember User Names**.
- 4) Click **Apply**.
- 5) Click **Close**.

## Activate or deactivate domain logon

Domain logon allows you to open the VPN connection directly on the Windows logon screen before you log on to Windows.



### Note

Domain logon is only supported for IPsec VPN connections. You cannot use domain logon with SSL VPN connections.

Using the domain logon allows network drives and other resources to be connected when you log on to Windows. The domain logon is helpful to avoid error messages and delays that can sometimes occur if resources are not available.

By default, all Gateways that you have contacted at least once are listed at Windows Logon when the domain logon feature is enabled. You can remove gateways from the logon screen by manually disabling the secure domain logon feature. Disable it through each gateway right-click menu on the **Gateways** tab of the **Forcepoint VPN Client Properties** dialog box.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Advanced** tab.
- 3) Select or deselect **Enable Secure Domain Logon**.
- 4) Click **Apply**.
- 5) Click **Close**.

### Related tasks

[Connect to a gateway from a Windows logon](#) on page 10

# Activate or deactivate random local VPN ports

For IPsec VPN connections, you can configure the Forcepoint VPN Client to select random local VPN ports when opening a VPN connection.



## Note

By default, the Forcepoint VPN Client uses local ports 500 and 4500 for VPN connections.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Advanced** tab.
- 3) Select or deselect **Use Random Local VPN Connection Ports**.
- 4) Click **Apply**.
- 5) Click **Close**.

# Activate or deactivate retry options

Some locations might require different connection settings than you used previously.

By default, the Forcepoint VPN Client has an automatic retry setting to help with some connection issues.

## Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Advanced** tab.
- 3) Select or deselect **Reconnect using different options after timeout**.
- 4) Click **Apply**.
- 5) Click **Close**.

# Close the VPN connection

There is usually no need to close the VPN connection when you stop using it. An unused connection automatically times out after a while.

Disconnecting the VPN manually changes the VPN status to **No VPN connection**. With any request that requires a VPN, an authentication prompt appears. To avoid the prompt, disable the Forcepoint VPN Client.

## Steps

- 1) Disconnect the VPN manually in one of the following ways:
  - Windows taskbar — Select **Disconnect** from the right-click menu for the Forcepoint VPN Client icon in the system tray on the Windows taskbar.
  - **Forcepoint VPN Client Properties** dialog box — Click **Disconnect** on the **Status** tab.
  - Windows user switch screen — Click **Disconnect** in the Windows user switch screen.

### Related tasks

[Connect to a gateway from a Windows logon on page 10](#)


# Disable the Forcepoint VPN Client

If necessary, you can disable the Forcepoint VPN Client so that it does not prompt you for authentication automatically.

When you disable the Forcepoint VPN Client, the status of the VPN changes to **No VPN connection (VPN Disabled)**. You can connect to a VPN manually following the usual procedure without specifically re-enabling the Forcepoint VPN Client. You are not able to use any resource through the VPN before you connect manually.

## Steps

- 1) You can turn off the prompt in one of the following ways:
  - Right-click the Forcepoint VPN Client icon in the Windows taskbar and select **Disable VPN**.
  - Click **Disable VPN** on the **Status** tab in the **Forcepoint VPN Client Properties** dialog box.
  - When the authentication prompt is automatically displayed, click the **Disable VPN** button in the **User Authentication** dialog box to disable the VPN.





**Related tasks**

[Connecting and authenticating](#) on page 10

# Troubleshooting VPN connections

If you are having problems with your VPN connections, consider these options for resolving the issue.

## Solving connectivity issues

You can resolve some connectivity issues by adjusting different VPN settings.

## Using different connection settings

Some connectivity problems can be solved by configuring the Forcepoint VPN Client to automatically try different combinations of retry settings.

The automatic retry setting is useful in dealing with network connections that severely restrict the allowed communications. In such situations, you can browse the Internet outside the VPN connection, but the Forcepoint VPN Client is unable to connect to the VPN gateway. The retry option is on the **Advanced** tab in **Forcepoint VPN Client Properties** dialog box.

**Related tasks**

[Activate or deactivate retry options](#) on page 23

## Enabling random ports

VPN connections might fail because the default local ports that the Forcepoint VPN Client uses for VPN connections, ports 500 and 4500, cannot be used in your environment.

You can configure the Forcepoint VPN Client to select random local VPN ports when opening a VPN connection.

**Related tasks**

[Activate or deactivate random local VPN ports](#) on page 23

## Change the Forcepoint VPN Client MTU

If you experience network problems, you can adjust the maximum transmission unit (MTU) size for your Forcepoint VPN Client installation.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.

- 2) Click the **Advanced** tab.
- 3) Select the **MTU** from the list or type in the MTU value.  
If you are not the administrator, the administrator tells you what value to use.
- 4) Click **Apply** and **Close**.
- 5) Restart the computer.

## Change the Forcepoint VPN Client MAC address

---

If you experience networking problems, you can adjust the MAC (media access control) address of your Forcepoint VPN Client. Changing the MAC address requires Windows administrator rights.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Advanced** tab.
- 3) Click **Select MAC Address**.  
The **MAC Address for Virtual IP Address** dialog box opens.  
Windows might display a security dialog box before the **MAC Address for Virtual IP Address** dialog box opens.
- 4) Select or type the correct MAC Address and click **Apply**.
- 5) Click **Close**.
- 6) Click **Apply** and **Close** in the **Forcepoint VPN Client Properties** dialog box.

## Collect diagnostic information

---

Diagnostics collect all the relevant information on how the Forcepoint VPN Client operates, including logs, network interface status, routes, and active connections.

The diagnostics are collected in a single archive for easy transfer. The file does not contain secret information such as passwords, but it does contain information related to the VPN configuration such as internal IP addresses. Depending on your operating environment, the file might need to be handled securely.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.

- 2) Click the **Diagnostics** tab.
- 3) Click **Collect Diagnostics**.  
The **Collect Diagnostics** dialog box opens and displays the progress of the data collection. You might see an additional dialog box open when system information is gathered.
- 4) When the data collection finishes, click **Save Diagnostics**.
- 5) Browse to the location where you want to save the file, enter a file name, and click **Save**.

## Capture network traffic

---

From the Forcepoint VPN Client, you can record the network traffic of the local computer during a problem situation to help with troubleshooting.

### Steps

- 1) In the system tray on the Windows taskbar, right-click the Forcepoint VPN Client icon, then select **Properties**.
- 2) Click the **Diagnostics** tab.
- 3) Click **Capture Traffic**.  
The **Capture Traffic** dialog box opens.
- 4) (Optional) Click **Browse** and browse to the folder where you want to save the traffic capture files.
- 5) Click **Start Capture**.  
The traffic capture begins.
- 6) Click **Stop Capture** when all traffic related to the problem has been recorded.
- 7) Click **Close** to close the **Capture Traffic** dialog box.

