



# **NGFW Security Management Center Appliance**

**7.1.10**

**Release Notes**

## Contents

- [About this release](#) on page 2
- [Build number and checksums](#) on page 2
- [System requirements on virtualization platforms](#) on page 3
- [Compatibility](#) on page 4
- [New features](#) on page 4
- [Enhancements](#) on page 5
- [Security updates](#) on page 7
- [Resolved and known issues](#) on page 7
- [Install the SMC Appliance](#) on page 7
- [Upgrade the SMC Appliance](#) on page 8
- [Find product documentation](#) on page 9

# About this release

This document contains important information about this software release for the Forcepoint NGFW Security Management Center Appliance (SMC Appliance). We strongly recommend that you read the entire document.

The SMC Appliance ships with pre-installed Forcepoint NGFW Security Management Center (SMC) software. The pre-installed SMC includes a Management Server and a Log Server. You can alternatively install the SMC Appliance software on a virtualization platform.



### Note

The SMC Appliance does not support high-availability for the Management Server or the Log Server.

## Upgrade deadline

Without installing the separate certificate update patch that is described in the [12281](#) Knowledge Base Article, this update can only be installed before 21st of January 2026 due to the expiration of the current update certificate. If you cannot install this update before 21st of January 2026, install the patch that is described in the [12281](#) Knowledge Base Article before that date to update only update certificates of your current installation. Otherwise, SMC Appliance upgrades or patches cannot be successfully installed after that date.

# Build number and checksums

The build number for SMC 7.1.10 is 11454. This release contains Dynamic Update package 2002.

Use checksums to make sure that files downloaded correctly.

### ■ 7.1.10P001.sap

```
SHA256SUM:
ebcc3f96ba8185d37c630d4617f419a22dc90db43666c72cc775e0057589e5da

SHA512SUM:
88c03db119e4ddab7e32e6d362dc9ece
7aeadd68d248dfc2c-fb99712509ade5a
08ecd555e53e236586aaf6e65febb82e
9c9f61aa01c17af05690b6c70a3e6292
```

### ■ 7.1.10U001.sap

```
SHA256SUM:
c8dc4c4debe3fd86dac29ece7250433c2184f8768b16e8b2b27c0b79689c30da

SHA512SUM:
985000f9dcb0da0208c18464222df3fb
7418b7bf276e990c806d2e677dc7eb47
02dc785cf0d618396e6ee4b02803f26d
0f021ba8e7e73a570d6826507d47d7e2
```

### ■ smca-7.1.10-11454.x86\_64.iso

```
SHA256SUM:
d7f50f7d48bfb483383bf0937f392bcc5e2911351da9d411a10255d2d7133806

SHA512SUM:
cf33c01f115e34012df15ee701bc7a0b
aa4c17fe271ece27cf7cc3dab7a6f0b1
fd81e85020214d54f9f0462f0dc940f5
9495cdfdf1ff1db51f875aa09ad3b6d8
```

## System requirements on virtualization platforms

As an alternative to using the SMC Appliance software on the pre-installed Forcepoint appliance, you can install the SMC Appliance software on a virtualization platform.



### CAUTION

To protect the privacy of your data, we recommend installing the NGFW Engines, SMC components, or SMC Appliance on a hypervisor that does not host any other virtual machines.

| Component          | Requirement                       |
|--------------------|-----------------------------------|
| Hypervisor         | VMware ESXi version 6.0 or higher |
| Memory             | 16 GB RAM                         |
| Virtual disk space | 128 GB                            |
| Interfaces         | At least one network interface    |

The .iso installation file that is used to install the SMC Appliance software on a virtualization platform is available only for major versions of the SMC Appliance. To install the maintenance version, first install the .iso for the major version, then upgrade to the maintenance version.

# Compatibility

SMC 7.1 can manage all compatible Forcepoint NGFW Engine versions up to and including version 7.1.



## Important

Some versions of Forcepoint NGFW have reached end-of-life status and no longer receive maintenance releases that contain security updates. Even though these Forcepoint NGFW versions might be compatible with the SMC, we recommend that you use a Long-Term Support version that is still supported. For more information about the Forcepoint NGFW lifecycle policy, see <https://support.forcepoint.com/ProductSupportLifeCycle>.

SMC 7.1 is all compatible with the Secure SD-WAN Engine versions up to and including version 7.1.

SMC 7.1 is compatible with Engine 6.8 or higher.

# New features

This release of the product includes these new features. For more information and configuration instructions, see the *Forcepoint Next Generation Firewall Product Guide* and the *Forcepoint Next Generation Firewall Installation Guide*.

## Forward traffic to specific tunnels or routers

By configuring the Forced Next Hop (FNH) option in the access rule you can now force forward traffic to a specific tunnel or router.

The advantage of using this option is that you can forward the matched traffic to a specific application that has the server behind a tunnel.

For more information, see *Configure Forced Next Hop routing* section in *Forcepoint Next Generation Firewall Product Guide*.

## SMC contact via FQDN

Support for using FQDN as the contact address to enable the engine to contact the SMC management server or log server. This can be beneficial when you run the SMC management server or log server in a cloud environment where managing long term public IP address is not feasible or is difficult.

For more information, see *Define Management Server or Log Server contact addresses*, and *Define contact address* sections in *Forcepoint Next Generation Firewall Product Guide*.

## Additional admin user authentication methods supported

The following admin user authentication methods are supported:

- OpenID Connect authentication by using an OpenID Connect provider.
- SAML authentication by using a SAML based identity provider.

For more information, see *Authenticate administrators using OpenID authentication method*, and *Authenticate administrators using SAML v2 authentication method* sections in *Forcepoint Next Generation Firewall Product Guide*.

## Improved SMC Domain Overview

The Domain Overview is updated to improve its scalability and usability to help users to easily navigate and find the domain information that they are looking for.

For more information, see *Log on to a Domain from the Domain Overview* section in *Forcepoint Next Generation Firewall Product Guide*.

## User Interface Themes

You can switch between light and dark theme for SMC.

For more information, see *Customize the Management Client layout* section in *Forcepoint Next Generation Firewall Product Guide*.

## DNS Sinkholing

You can now configure DNS sinkholing for UDP and TCP service elements. One of the scenarios where this feature can be useful is, when there is an infected machine in the internal network. It can be identified by using the DNS sinkholing.

For more information, see *Create custom service elements* section in *Forcepoint Next Generation Firewall Product Guide*.

# Enhancements

This release of the product includes these enhancements.

## Enhancements in SMC version 7.1.0

| Enhancement                                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| BGP Monitoring Protocol (BMP) Configuration | <p>Support for BMP configuration options from the Dynamic Routing Editor. It is used to monitor BGP sessions and send the monitored data from BGP routers to the network management entities. Also, when configured the log events includes the information for the configured options, and which in turn helps to make correlation of BMP and engine logs easy for analytics.</p> <p>For more information, see <i>Create core elements for dynamic routing</i>, and <i>Enable BGP on the Engine, Engine Cluster, or Virtual Engine</i> sections in <i>Forcepoint Next Generation Firewall Product Guide</i>.</p> |

| Enhancement                                         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-----------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Improved Application Health Monitoring              | <p>The Application Health Monitoring feature now comes with the following support:</p> <ul style="list-style-type: none"> <li>Enhanced engine monitoring and better support for non-TCP traffic, that is there is now support for applications that use UDP for data transport.</li> <li>Visibility into application health history and health status history of network applications.</li> <li>Better ISP link status monitoring.</li> <li>Application health status history.</li> </ul> <p>For more information, see <i>Application Health Monitoring Dashboard</i> section in <i>Forcepoint Next Generation Firewall Product Guide</i>.</p>                                                                                                                                                                                                                                                                                                                       |
| Improved SD-WAN algorithms and link selection logic | <p>The following updates have been done to provide for better user experience:</p> <ul style="list-style-type: none"> <li>Engine logic is updated to avoid too much packet loss before the traffic is sent to the better links.</li> <li>The QoS link value is tuned to make QoS link value selection feature to work as intended.</li> </ul> <p>Also, the <b>Default SD-WAN Link Balancing Preference</b> option is made available to allow you to set the preferences on how the traffic is balanced over the links for each engine.</p> <p>For more information, see <i>Create Link Usage Profile elements</i> section in <i>Forcepoint Next Generation Firewall Product Guide</i>.</p>                                                                                                                                                                                                                                                                           |
| Tunnel interface now supports multiple IP addresses | <p>It is now possible to add multiple IP addresses (that can be of types IPv4 and IPv6) for tunnel interfaces.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| IPFIX forwarding                                    | <p>When you export IPFIX information, the following new IPFIX Element IDs are now supported:</p> <ul style="list-style-type: none"> <li>EID 5 ipClassOfService</li> <li>EID 58 vlanId (source VLAN)</li> <li>EID 59 postVlanId (destination VLAN)</li> <li>EID 60 ipVersion</li> <li>EID 89 forwardingStatus</li> <li>EID 90 mplsVpnRouteDistinguisher</li> <li>EID 131 exporterIPv6Address</li> </ul> <div>  <p><b>Note</b></p> <ol style="list-style-type: none"> <li>EID 90 mplsVpnRouteDistinguisher is exported, only when BMP monitoring is configured for the engine that originates the log entries.</li> <li>The following IPFIX element IDs are only generated by engine version 7.1.0 or later: <ul style="list-style-type: none"> <li>EID 5 ipClassOfService</li> <li>EID 89 forwardingStatus</li> <li>EID 90 mplsVpnRouteDistinguisher</li> </ul> </li> </ol> </div> |

# Security updates

---

For information about third-party packages and associated vulnerabilities included with SMC in this product release, see Knowledge Base article [11241](#).

# Resolved and known issues

---

For a list of resolved and known issues in this product release, see Knowledge Base article [4751](#).

# Install the SMC Appliance

---

Use these high-level steps to install the SMC Appliance.

For detailed information about installing the SMC Appliance and the NGFW Engines, see the *Forcepoint Next Generation Firewall Installation Guide*. All guides are available for download at <https://support.forcepoint.com/s/article/Documentation-Featured-Article>.

## Steps

- 1) Turn on the SMC Appliance.
- 2) Select the keyboard layout for accessing the SMC Appliance on the command line.
- 3) Accept the EULA.
- 4) Enter the account name and password.  
For credential requirements, see the *Forcepoint Next Generation Firewall Installation Guide*.
- 5) Make your security selections.
- 6) Complete the network interface and network setup fields.
- 7) Enter a host name for the Management Server and set DNS servers.
- 8) Select the time zone.
- 9) (Optional) Configure NTP settings.
- 10) After the SMC Appliance has restarted, install the Management Client from Forcepoint support or from P patch.  
As an alternative to installing the Management Client locally, you can use SMC Web Access to start and run the Management Client in a web browser. SMC Web Access is enabled by default for new installations of the SMC Appliance.

- 11) Import the licenses for all components.  
You can generate licenses at <https://stonesoftlicenses.forcepoint.com>.
- 12) Create the NGFW Engine elements, then install and configure the NGFW Engines.

## Upgrade the SMC Appliance

Use an upgrade patch to upgrade the SMC Appliance from a previous version to version 7.1.10.

There are two kinds of SMC Appliance patches:

- Hotfix patches include improvements and enhancements for the current SMC Appliance version. Hotfix patch files use the letter P as a separator between the version number and the patch number. Example: 7.1.1P001
- Upgrade patches upgrade the SMC Appliance to a new version.  
Upgrade patch files use the letter U as a separator between the version number and the patch number.  
Example: 7.1.1U001

We recommend checking the availability of SMC Appliance patches regularly, and installing the patches when they become available. For detailed information about installing SMC Appliance patches, see the *Forcepoint Next Generation Firewall Installation Guide*.

- SMC 7.1 requires an updated license.
  - If the automatic license update function is in use, the license is updated automatically.
  - If the automatic license update function is not in use, request a license upgrade on our website at <https://stonesoftlicenses.forcepoint.com>. Activate the new license using the Management Client before upgrading the software.
- The SMC Appliance must be upgraded before the NGFW Engines are upgraded to the same major version.
- You can upgrade from the following SMC versions; however, only the latest maintenance release and LTS versions are tested. Hence, It is recommended to upgrade to the latest LTS release of SMC, regardless of NGFW Engine versions being managed. For detailed information on how to upgrade SMC Appliance to a new version, see *Forcepoint Next Generation Firewall Installation Guide*.
  - 6.10.13 - 6.10.19
  - 7.1.1 - 7.1.9

For detailed information on how to upgrade the SMC Appliance from a version that is not listed above to a newer version, see Knowledge Base article [41318](#).

- If you configured SNMP for the SMC Appliance before upgrading to version 6.4.0 or higher, you must configure SNMP again.

You can upgrade the SMC Appliance using the Management Client or using the appliance maintenance and bug remediation (AMBR) patching utility on the command line of the SMC Appliance. For detailed information, see *Forcepoint Next Generation Firewall Product Guide*.

# Find product documentation

In the Forcepoint Customer Hub, you can find information about a released product, including product documentation, technical articles, and more.

You can get additional information and support for your product in the Forcepoint Customer Hub at <https://support.forcepoint.com>. There, you can access product documentation, release notes, Knowledge Base articles, downloads, cases, and contact information.

You might need to log on to access the Forcepoint Customer Hub. If you do not yet have credentials, create a customer account. To create a customer account, navigate to the Customer Hub Home page, and then click the **Create Account** link.

## Product documentation

Every Forcepoint product has a comprehensive set of documentation.

- *Forcepoint Next Generation Firewall Product Guide*
- Forcepoint Next Generation Firewall online Help



### Note

By default, the online Help is used from the Forcepoint help server. If you want to use the online Help from a local machine (for example, an intranet server or your own computer), see Knowledge Base article [10097](#).

- *Forcepoint Next Generation Firewall Installation Guide*

Other available documents include:

- *Forcepoint Next Generation Firewall Hardware Guide* for your model
- *Forcepoint NGFW Security Management Center Appliance Hardware Guide*
- *Forcepoint Next Generation Firewall Quick Start Guide*
- *Forcepoint NGFW Security Management Center Appliance Quick Start Guide*
- *Forcepoint NGFW SMC API User Guide*
- *Forcepoint VPN Client User Guide* for Windows or Mac
- *Forcepoint VPN Client Product Guide*
- *Forcepoint NGFW Manager and VPN Broker Product Guide*

