



Web Security

DLP

Email Security

8.5.x

Security Solutions Upgrade Guide

© 2025 Forcepoint

Forcepoint and the FORCEPOINT logo are trademarks of Forcepoint.
All other trademarks used in this document are the property of their respective owners.

Published 27 June 2025

Every effort has been made to ensure the accuracy of this document. However, Forcepoint makes no warranties with respect to this documentation and disclaims any implied warranties of merchantability and fitness for a particular purpose. Forcepoint shall not be liable for any error or for incidental or consequential damages in connection with the furnishing, performance, or use of this manual or the examples herein. The information in this documentation is subject to change without notice.

Contents

1 Upgrading Forcepoint Security Solutions.....	5
Introduction.....	5
Before upgrading Forcepoint security solutions.....	6
Upgrade procedure for Forcepoint security solutions.....	8

Chapter 1

Upgrading Forcepoint Security Solutions

Contents

- Introduction on page 5
- Before upgrading Forcepoint security solutions on page 6
- Upgrade procedure for Forcepoint security solutions on page 8

Introduction

This guide describes how to upgrade a Forcepoint deployment with multiple modules —web, email, or data—to v8.5.x (web and email) or v8.8.x (data). For information on upgrading systems that include stand-alone installations of data, email, or web protection solutions, refer to the [Deployment and Installation Center](#).

Forcepoint security solutions can only be upgraded to the latest version from certain versions. Check the current release notes or upgrade guides for your products to verify that upgrade is possible.

Because Forcepoint Email Security includes Forcepoint DLP components, the upgrade procedure for combined web and email solutions is the same as the upgrade procedure for all Forcepoint modules.

Certain older V10000 and V5000 appliances are not supported with version 8.0.0 and higher. See [Appliances supported with version 8.x](#).

To upgrade to the latest versions, see:

- [System requirements for this version](#)
- [Before upgrading Forcepoint security solutions](#)
- [Upgrade procedure for Forcepoint security solutions](#)

Perform the upgrade in the order described. This sequence is critical, because if you upgrade supplemental servers or agents before the management server, they stop communicating. If you upgrade the management server first, it continues communicating with the components until they are upgraded.



Note

Direct upgrade to Forcepoint Web Security On-prem v8.5.7 is not supported for software customers. Version 8.5.7 is compatible only with Red Hat Enterprise Linux 8 and Oracle Linux 8. The underlying operating system must be upgraded to a supported version before installing Forcepoint Web Security On-prem v8.5.7.

Related concepts

- [Before upgrading Forcepoint security solutions on page 6](#)
- [Upgrade procedure for Forcepoint security solutions on page 8](#)

Before upgrading Forcepoint security solutions

The upgrade process guides you through upgrading **all** components on the selected machine.

- You cannot choose which components to upgrade.
- Partial upgrades are not supported.
- Upgrades must proceed in the exact order listed in *Upgrade procedure for Forcepoint security solutions*.

When upgrading the Forcepoint management server, if upgrade fails for any component **except** Forcepoint Management Infrastructure, you can either continue to upgrade the rest of the components or exit the process and modify component settings.

- You cannot continue if the infrastructure upgrade fails.
- You cannot roll back a component that was upgraded successfully.

After upgrade, your system has the same configuration as before the upgrade. Apart from the option to edit the Forcepoint Email Security database IP address if it has changed since installation, the upgrade process does not allow you to change your configuration or settings.

Related concepts

[Upgrade procedure for Forcepoint security solutions on page 8](#)

Preparing for the upgrade

- Read the relevant release notes.
 - [Release Notes for Forcepoint Web Security and Forcepoint URL Filtering](#)
 - [Release Notes for Forcepoint DLP](#)
 - [Release Notes for Forcepoint Email Security](#)
 - [Release Notes for Forcepoint Appliances](#)
- Verify the current deployment. Unless instructed otherwise by Forcepoint Technical Support, ensure that your system is functional prior to upgrade, and that required network interfaces have reliable connections to Forcepoint components and the Internet. The upgrade process does not repair a non-functional system.
- Ensure the time set on all appliances is synchronized prior to upgrade.
- If you are not already familiar with the preparation required for upgrading off- appliance components, review the requirements before upgrading your appliances.
- Verify the system requirements for the version to which you are upgrading. See [System requirements for this version](#).
- Prepare Windows components. See [Preparing for installation](#) for an explanation of general preparations for upgrading the Windows components in your security solution.
- Ensure that your firewall is configured correctly so that the ports needed for proper protection are open. See [Default ports for on-premises Forcepoint security solutions](#).
- Prepare Microsoft Azure virtual network if you are upgrading to Forcepoint Email Security in Azure. See [Installing Forcepoint Email Security in Microsoft Azure](#).

- Prepare for service disruption during upgrade. Appliance services are not available while the upgrade is applied, continuing until the appliances finishes its final restart. Service is not disrupted while the off-appliance components are upgraded.
- If you are using link aggregation and plan to enable VLAN support after upgrade, disable link aggregation before enabling VLAN support on the blade or chassis. VLAN is only available on X Series appliances.
- If you are already using Virtual Machines (VMs) for Forcepoint Security Manager or for Microsoft SQL Server, take a snapshot of the VMs before you start a Forcepoint upgrade.
- If you have a remote database, ensure that the SQL account has a sysadmin role.
- Back up all of your Forcepoint components before starting the upgrade process, see [Backup and Restore FAQ](#).

The Backup and Restore FAQ includes instructions for backing up all of the pieces that make up Forcepoint Web Security Hybrid Module (formerly Web Security Gateway Anywhere) on all platforms:

- Forcepoint Management Infrastructure
- Web Security components
- Content Gateway
- Data Security components
- (Appliance upgrades only) Uninstall the following hotfix:
 - If you have any appliance with Hotfix 200 (Spectre/Meltdown Hotfix) installed, you must uninstall the hotfix before upgrading to v8.5. After upgrading, reinstall Hotfix 200 on the new version.
- (Appliance upgrades only) Install the following hotfix:
 - If you are a Forcepoint V5000 G2R2 customer upgrading from v8.4 to v8.5, you must install 8.4 Appliance Hotfix 101 (APP-8.4.0-101) before upgrading.
- (Forcepoint Email Security upgrades) Back up and remove tomcat log files and remove temporary manager files (optional; recommended to facilitate timely Forcepoint Security Manager upgrade). Use the following steps:
 - 1) Log onto the Windows server where the Forcepoint Security Manager resides.
 - 2) Navigate to the `C:\Program Files (x86)\ Websense\Email Security\ESG Manager\tomcat\logs` directory
 - 3) Copy `C:\Program Files (x86)\ Websense\Email Security\ESG Manager\tomcat\logs` to another location (for example, to `C:\WebsenseBackup\Email`), and then delete it in the directory mentioned in step 2.
 - 4) Navigate to the `C:\Program Files (x86)\ Websense\Email Security\ESG Manager\tomcat\tempEsgUploadFileTemp` directory.
 - 5) Delete all the downloadFile* files.
- Inventory all customizations and make a plan for restoring any that are required. Customizations are not retained through the upgrade process. After your upgrade, contact Forcepoint Technical Support for assistance with restoring files from your pre-upgrade file system. Customizations can include:
 - Custom patches
 - Hand updated files
 - Extra packages added
 - Extra files added, binary or configuration
- Back up appliance configuration and settings. It is critical to perform a full appliance configuration backup and save it to a filestore.
 - 1) Log onto the CLI and elevate to **config** mode.

- 2) To perform an immediate full backup, use:
create backup now --location filestore_alias [--desc "<description>"]
- 3) Include a unique description to make it easier to identify backup files that may have very similar names and dates.

Upgrade procedure for Forcepoint security solutions

When upgrading multiple Forcepoint components, you must upgrade them in the following order.

For information on upgrading systems that include standalone installations of data, email, or web protection solutions, refer to the [Deployment and Installation Center](#).

Forcepoint Security Solutions v8.5 does not support dual-mode V Series appliances (that is, appliances that host Forcepoint Email Security and Forcepoint Web Security, or Forcepoint Email Security and Forcepoint URL Filtering). If you are upgrading a dual-mode appliance, see [V Series Dual-Mode Appliance Upgrade Guide](#).

This procedure covers the steps required to upgrade either the all on-premises security solutions or Web and Email solutions (given that Email includes Data components).

Related concepts

- [Step 4: Upgrade Log Servers](#) on page 14
- [Step 6: Upgrade appliances](#) on page 20
- [Step 7: Upgrade additional components](#) on page 21

Related tasks

- [Step 1: Upgrade the Policy Broker machine](#) on page 8
- [Step 2: Upgrade additional Policy Server machines](#) on page 10
- [Step 3: Upgrade additional Filtering Service and User Service machines](#) on page 12
- [Step 5: Upgrade the management server](#) on page 14

Step 1: Upgrade the Policy Broker machine

You must upgrade the machine that hosts **Web Policy Broker** first, regardless of which other components are on the machine. Policy Broker may reside on:

- A **full policy source** appliance
- A Windows Server 2008 R2 SP1, 2012, or 2012 R2 machine.
- A RHEL 6.5 or later, 7.0, 7.1, or 7.2 machine.

Any other components on the Policy Broker machine are upgraded along with Policy Broker.

If your configuration includes a primary Policy Broker and one or more replica Policy Brokers, you **must** upgrade the primary Policy Broker first.

Upgrade replica Policy Brokers after the primary has been upgraded and before attempting to upgrade any Policy Servers associated with the replicas. If Policy Server is installed on the Policy Broker machine, it is upgraded at the same time.

If Policy Broker resides on the management server, running the Forcepoint Security Installer also upgrades the infrastructure and web, data, and email management components as described in *Step 5: Upgrade the management server*. Ensure you also follow the steps in *Post-upgrade steps* to configure the management server.

For a software installation, run the Forcepoint Security Installer or Web Linux installer. The instructions in this section cover the upgrade of a Windows machine. For instructions on upgrading an appliance or a Linux machine, see the [Upgrade Guide: Forcepoint Web Security](#).

Steps

- 1) Make sure that no administrators are logged on to the management console.
- 2) Log on to the installation machine with an account having **domain** and **local** administrator privileges.



Important

If you are upgrading Log Server on this machine and it uses a Windows trusted connection to access the Log Database, you must log on to this machine using the same trusted account.

- 3) Close all applications and stop any antivirus software.



Warning

Be sure to close the Windows Event Viewer, or the upgrade may fail.

- 4) Download the Forcepoint Security Windows Installer **Forcepoint856Setup.exe**:
 - a) Log on to the Forcepoint [Downloads](#) page.
 - b) Select **Web Security** from **Products**.
 - c) Click **On-Premises (Web)**.
 - d) Click **Forcepoint Web Security 8.5.6 for Windows (required)** from the **Installer** list.



Note


Only latest version is available under **Installer** list. If you want to select the previous versions, then use [Click here](#).

- e) Click **Download** in the **Product Installer** page to download the Forcepoint Security Installer `Forcepoint856Setup.exe`.

The installer and its extracted files require approximately 7 GB of disk space.

- 5) Right-click **Forcepoint856Setup.exe** and select **Run as administrator** to launch the installer. A progress dialog box appears, as files are extracted.

The installer detects Web Security components from an earlier version and asks whether you want to proceed.

- 6) Click **OK**.
- 7) On the installer **Introduction** screen, click **Next**.
The **Installer Dashboard** remains on-screen, behind the installer screens mentioned in the remaining steps.
- 8) On the **Upgrade** screen, select **Start the upgrade**, then click **Next**.
- 9) Accept the subscription agreement. When you click **Next**, a *Stopping All Services* progress message appears. Wait for services to be stopped.
The **Pre-Upgrade Summary** screen appears when the services have been stopped.
In some cases, the installer may be unable to stop the services. If this occurs, you are prompted to stop them manually (you do not need to exit the installer to do this). Use the Windows Services tool to stop the services, then return to the installer.
- 10) On the **Pre-Upgrade Summary** screen, review the list of components that will be upgraded, and then click **Next**.
Critical files are backed up and install properties initialized, and then the upgrade begins.
If Policy Broker resides on the management server, or on the same machine as Log Server, the upgrade process checks for a required version of Microsoft SQL Server Native Client and related tools and installs them, if necessary.
- 11) Wait for the **Upgrade Complete** screen to appear. Click **Done** to exit the installer.
- 12) Reboot the machine.
 **Important**
The machine must be rebooted to complete the upgrade process.
- 13) If you stopped your antivirus software, restart it.

Related tasks

[Step 5: Upgrade the management server](#) on page 14

[Post-upgrade steps](#) on page 20

Step 2: Upgrade additional Policy Server machines

The central Policy Server resides on the same machine as Policy Broker and was automatically upgraded in the previous section.

If you have additional Policy Server instances, upgrade them next, regardless of what other services reside on the machines. Policy Server may reside on:

- **User directory and filtering** appliances
- Windows Server 2008 R2 SP1, 2012, or 2012 R2 machines

- RHEL 6.5 and later, 7.0, 7.1, or 7.2 machines

The instructions in this section cover the upgrade of a Windows machine, using the Forcepoint Security Installer. For instructions on upgrading an appliance or a Linux machine, use the v8.5 upgrade patch. See [Upgrade Guide: Forcepoint Web Security](#).

Steps

- 1) Make sure that no administrators are logged on to Forcepoint Security Manager.
- 2) Log on to the installation machine with an account having **domain** and **local** administrator privileges.



Important

If you are upgrading Log Server on this machine and it uses a Windows trusted connection to access the Log Database, you must log on to this machine using the same trusted account.

- 3) Close all applications and stop any antivirus software.



Warning

Be sure to close the Windows Event Viewer, or the upgrade may fail.

- 4) Download the Forcepoint Security Windows Installer **Forcepoint856Setup.exe**:
 - a) Log on to the Forcepoint [Downloads](#) page.
 - b) Select **Web Security** from **Products**.
 - c) Click **On-Premises (Web)**.
 - d) Click **Forcepoint Web Security 8.5.6 for Windows (required)** from the **Installer** list.



Note

Only latest version is available under **Installer** list. If you want to select the previous versions, then use [Click here](#).

- e) Click **Download** in the **Product Installer** page to download the Forcepoint Security Installer `Forcepoint856Setup.exe`.

The installer and its extracted files require approximately 7 GB of disk space.

- 5) Right-click **Forcepoint856Setup.exe** and select **Run as administrator** to launch the installer. A progress dialog box appears, as files are extracted.
The installer detects Web components from an earlier version and asks how you want to proceed.
- 6) Click **OK**.
- 7) On the installer **Introduction** screen, click **Next**.
The **Installer Dashboard** remains on-screen, behind the installer screens mentioned in the remaining steps.

- 8) On the **Upgrade** screen, select **Start the upgrade**, then click **Next**.
- 9) Accept the subscription agreement. When you click **Next**, a *Stopping All Services* progress message appears. Wait for services to be stopped.
The **Pre-Upgrade Summary** screen appears when the services have been stopped.
In some cases, the installer may be unable to stop the services. If this occurs, you are prompted to stop them manually (you do not need to exit the installer to do this). Use the Windows Services tool to stop the services, then return to the installer.
- 10) On the **Pre-Upgrade Summary** screen, review the list of components that will be upgraded, and then click **Next**.
Critical files are backed up and install properties initialized. And then the **Installing Forcepoint** screen appears.
- 11) Wait for the **Upgrade Complete** screen to appear. Click **Done** to exit the installer.
- 12) Reboot the machine.

**Important**

The machine must be rebooted to complete the upgrade process.

- 13) If you stopped your antivirus software, restart it.

Step 3: Upgrade additional Filtering Service and User Service machines

If you have additional Filtering Service or User Service instances, upgrade them next, regardless of what other services reside on the machines. Filtering Service and User Service may reside on:

- Windows Server 2008 R2 SP1, 2012, or 2012 R2 machines
- RHEL 6.5 or later, 7.0, 7.1, or 7.2 machines

Filtering Service and Network Agent may also reside on **filtering only** appliances.

If you have filtering only appliances in your deployment, upgrade these appliances after the corresponding full policy source or user directory and filtering appliance has been upgraded. This is because appliances that have instances of Policy Server must be upgraded before you upgrade any components that point to it.

The instructions in this section cover the upgrade of a Windows machine. For instructions on upgrading an appliance or a Linux machine, see [Upgrade Guide: Forcepoint Web Security](#).

Make sure that no administrators are logged on to the management console.

Steps

- 1) Log on to the installation machine with an account having **domain** and **local** administrator privileges.



Important

If you are upgrading Log Server on this machine and it uses a Windows trusted connection to access the Log Database, you must log on to this machine using the same trusted account.

- 2) Close all applications and stop any antivirus software.



Warning

Be sure to close the Windows Event Viewer, or the upgrade may fail.

- 3) Download the Forcepoint Security Windows Installer **Forcepoint856Setup.exe**:
 - a) Log on to the Forcepoint [Downloads](#) page.
 - b) Select **Web Security** from **Products**.
 - c) Click **On-Premises (Web)**.
 - d) Click **Forcepoint Web Security 8.5.6 for Windows (required)** from the **Installer** list.




Note

Only latest version is available under **Installer** list. If you want to select the previous versions, then use [Click here](#).

- e) Click **Download** in the **Product Installer** page to download the Forcepoint Security Installer `Forcepoint856Setup.exe`.

The installer and its extracted files require approximately 7 GB of disk space.

- 4) Right-click **Forcepoint856Setup.exe** and select **Run as administrator** to launch the installer. A progress dialog box appears, as files are extracted.
The installer detects Web Security components from an earlier version and asks how you want to proceed.
- 5) Click **OK**.
- 6) On the installer **Introduction** screen, click **Next**.
Note the **Installer Dashboard** remains on-screen, behind the installer screens mentioned in the remaining steps.
- 7) On the **Upgrade** screen, select **Start the upgrade**, then click **Next**.

- 8) Accept the subscription agreement. When you click **Next**, a *Stopping All Services* progress message appears. Wait for services to be stopped.
The **Pre-Upgrade Summary** screen appears when the services have been stopped.
In some cases, the installer may be unable to stop the services. If this occurs, you are prompted to stop them manually (you do not need to exit the installer to do this). Use the Windows Services tool to stop the services, then return to the installer.
- 9) On the **Pre-Upgrade Summary** screen, review the list of components that will be upgraded, and then click **Next**.
Critical files are backed up and install properties initialized. And then the **Installing Forcepoint** screen appears.
- 10) Wait for the **Upgrade Complete** screen to appear. Click **Done** to exit the installer.
- 11) Reboot the machine.
 **Important**
The machine must be rebooted to complete the upgrade process.
- 12) If you stopped your antivirus software, restart it.

Step 4: Upgrade Log Servers

Upgrade the Web and Email Log Server machines, if they have not already been upgraded with other components. Any other services on the machine are also upgraded in the correct order.

If these components are on separate machines, it does not matter which is upgraded first.



Important

Make sure that no Email Log Database or Web Log Database jobs are running while the Log Server instances are being upgraded.

For information on Web Security Log Server, see [Upgrade Guide: Forcepoint Web Security](#).

For information on Email Security Log Server, see [Upgrading to Forcepoint Email Security v8.5](#).

Step 5: Upgrade the management server

If you have not already upgraded the management server in the course of upgrading another component, use the following steps to upgrade the management server machine.

- Whenever possible, upgrade the management server before any other Data components. This ensures that policy engines continue to function until they are upgraded themselves.
New policies cannot be deployed to the policy engines until they are upgraded to the same version as the management server.

- If you need to upgrade a policy engine before upgrading the management server— because the policy engine resides on a full policy source appliance—detection of fingerprinted content might not work on the appliance until the management server is upgraded.
The policy engine embedded in Content Gateway and Email products continues to monitor the old Web and Email DLP policies and block/permit accordingly.

Steps

- 1) Make sure that no administrators are logged on to the management console.
- 2) Log on to the installation machine with an account having **domain** and **local** administrator privileges.
- 3) Close all applications and stop any antivirus software.



Warning

Be sure to close the Windows Event Viewer, or the upgrade may fail.

- 4) Go to <https://support.forcepoint.com/s/>.
- 5) Click **Downloads**.
- 6) In **Products**, select **Data Loss Prevention (DLP)**.
- 7) Select **DLP Core**.
- 8) On the list of installers, click **Forcepoint Security Manager for DLP v10.3**.



Note

For older version installers, click **Click here**, and then select the installer from the desired version.

- 9) On the **Product Installer** page, click **Download**.
The Forcepoint Security Installer **ForcepointDLP1030Setup.exe** downloads.
- 10) Right-click **ForcepointDLP1030Setup.exe** and select **Run as administrator** to launch the installer. A progress dialog box appears as files are extracted.
The installer detects components from an earlier version and asks how you want to proceed.
- 11) Click **OK**.
- 12) On the installer **Introduction** screen, click **Next**.
The **Installer Dashboard** remains on-screen, behind the installer screens that appear in subsequent stages of the upgrade.

- 13) Follow the screens in the upgrade wizard as described in the sections below:
 - *Management Infrastructure*
 - *Forcepoint Web Security*
 - *Forcepoint DLP*
 - *Forcepoint Email Security*
- 14) Wait for the **Upgrade Complete** screen to appear. Click **Done** to exit the installer.
- 15) Reboot the machine.



Important

You may be prompted to restart the machine after each component is upgraded. This is optional. You may prefer to restart the machine once after all components are upgraded.

- 16) If you stopped your antivirus software, restart it.
- 17) Follow the instructions in *Post-upgrade steps*.

Related tasks

[Post-upgrade steps](#) on page 20

Related reference

[Management Infrastructure](#) on page 16
[Forcepoint Web Security](#) on page 17
[Forcepoint DLP](#) on page 18
[Forcepoint Email Security](#) on page 19

Management Infrastructure

The Forcepoint Management Infrastructure provides basic framework for all of the management components that make up the Forcepoint Security Manager. This framework includes a central settings database that stores shared configuration (like administrator directory and account information) for all management modules, as well as other internal shared services.

The infrastructure upgrade wizard contains the following screens.

Wizard Screen	Fields
Welcome	<p>Welcomes you to the installation and upgrade wizard.</p> <ol style="list-style-type: none"> 1) Click Next to begin the upgrade process. The system checks disk space requirements. 2) When prompted, click Next to launch the installation wizard.

Wizard Screen	Fields
Pre-Installation Summary	<p>Shows:</p> <ul style="list-style-type: none"> ■ The destination folder for the installation files. ■ The name of the SQL Server machine and the user name of an authorized database administrator. ■ The IP address of the Forcepoint management server and administrator credentials. <p>Click Next to accept the properties.</p>
Installation	<p>Shows upgrade progress.</p> <p>The system stops processes, copies new files, updates component registration, removes unused files, and more.</p> <p>A popup message appears at this stage, warning that you must also upgrade all modules. This popup may be hidden behind the main installer window. If your installation appears to freeze, locate the hidden popup by moving the main installer window, and click OK to proceed with the installation.</p>
Summary	<p>Summarizes your system settings after module upgrade is complete, including:</p> <ul style="list-style-type: none"> ■ The destination folder for the installation files. ■ The name of the SQL Server machine and the user name of an authorized database administrator. ■ The IP address of the Forcepoint management server and administrator credentials. <p>Click Finish to complete the upgrade for this module.</p>

Forcepoint Web Security

The Web Security upgrade wizard contains the following screens.

Wizard Screen	Fields
Introduction	<p>Welcomes you to the upgrade wizard. Click Next to continue.</p>
Upgrade	<p>Select Start the upgrade, then click Next.</p> <ol style="list-style-type: none"> 1) Accept the subscription agreement and click Next. 2) The installer proceeds to stop all Forcepoint services.
Pre-Upgrade Summary	<p>Provides a list of components that will be upgraded. Click Next to start the upgrade.</p> <p>The installer backs up critical files.</p>

Wizard Screen	Fields
Installing	Shows installation progress. When complete, the installer configures your software. This can take up to 10 minutes.
Upgrade Complete	You are notified when installation of this module is complete. Click Done to exit the installer.

Forcepoint DLP

Before running the data upgrade wizard, the installer validates system requirements to ensure your upgrade will be successful.

The pre-upgrade check validates hardware requirements, credentials for your SQL management database, endpoint security certificates, manager configuration, administrator upgrade permissions, and your database structure. As it proceeds, it reports whether a step succeeded or failed, or it gives you a warning.

If there is a failure, the upgrade stops. For details, see `\AP-DATA- PreUpgradeTests.log` in the directory where you installed Forcepoint DLP.

If there are only warnings, you have the option to proceed with the upgrade or stop it. If you continue, your system may behave unexpectedly, but this will not have a critical impact.

If the pre-upgrade check succeeds or if you proceed with warnings, the Forcepoint DLP wizard is launched, followed by wizards for each installed component.

The Data Security upgrade wizard contains the following screens.

Wizard Screen	Fields
Welcome	Welcomes you to the installation and upgrade wizard. The system checks the disk space on the machine. When prompted, click Next to launch the installation wizard.
Installation Confirmation	Verify your system settings and click Install to continue the upgrade.
Installation	Shows the progress of the installation. The system stops processes, checks ports, copies new files, updates component registration, removes unused files, and more. In certain circumstances, you may receive an internal SQL error. If you do, do not click OK until you have resolved the issue with Forcepoint Technical Support. If you continue prematurely, you can cause problems with your reporting database.

Wizard Screen	Fields
Summary	<p>Summarizes your system settings when installation of this module is complete.</p> <ol style="list-style-type: none"> 1) Click Done and you are prompted to update your predefined policies and content classifiers. 2) Click OK to install the updates. You're shown the status of the updates, the items being updated, and details such as how many policies are updated, deleted, or added. 3) Click Close when the updates are complete.

Forcepoint Email Security

The Email Security upgrade wizard contains the following screens.

Wizard Screen	Fields
Introduction	Welcomes you to the upgrade wizard. Click Next to continue.
Select Components	Shows the components that will be upgraded (those that are currently installed). Click Next to continue.
Configuration	Shows the IP address of the database engine configured to manage the Email Security Log Database and the logon type. If you have changed the database since your previous installation, modify the settings here.
Pre-Installation Summary	<p>Shows:</p> <ul style="list-style-type: none"> ■ The components to be installed ■ The pre-existing and new version numbers ■ The destination folder for the installation files ■ The required and available disk space <p>Click Install to begin the upgrade.</p>
Installation	<p>Shows that the installation is progressing.</p> <p>The management component is upgraded on the Forcepoint management server.</p> <p>The Email Security Log Server is upgraded on machines where it is found.</p> <p>When complete, the installer configures your Forcepoint Email Security software. This can take up to 10 minutes.</p>
Summary	You are notified when installation of this module is complete. Click Done to exit the installer.

Post-upgrade steps

After the Forcepoint management server upgrade is complete:

Steps

- 1) Restart the management server.
- 2) Log onto Forcepoint Security Manager.
- 3) Click **Data** in the Security Manager toolbar to select the Data Security module.
- 4) Follow the prompts that appear for updating data loss protection policies and classifiers.
Depending on the number of policies you have, this can take up to an hour. During this time, do not restart the server or any of the services.
- 5) If you removed applications from Forcepoint DLP's predefined endpoint application groups prior to upgrade, go to the **Main > Resources > Endpoint Application Groups** page after logging on and remove them again. The upgrade process restored these to their original state.
- 6) Click **Deploy**.
- 7) Click **Email** in the Security Manager toolbar to select the Email Security module.
- 8) Go to the page **Settings > General > Database Downloads** and click **Update Now** to perform an immediate database download update.

Step 6: Upgrade appliances

Upgrade all appliances that have not been upgraded in the above steps. This can be done in any order, and can be completed in parallel.

If you have deployed Forcepoint Email Security in cluster mode, release all appliances from the cluster before performing an upgrade. Upgrade or migrate each appliance as needed, then rebuild your cluster after the process is complete.

The Email MTA continues to function after the management server upgrade, but the logs are cached on the appliance until Forcepoint Email Security is upgraded as well. For best practice, redirect email traffic to another MTA as cached messages may be lost otherwise.

For more information, see the following:

- [V Series Appliance Upgrade Guide](#)
- [X Series Appliance Upgrade Guide](#)
- [Upgrading Forcepoint Email Security](#)

Step 7: Upgrade additional components

Once you have completed the above steps, you can upgrade any additional Web and Data software components and client components:

- 1) Upgrade any additional software instances of Network Agent and Content Gateway. If these components run on Forcepoint V Series, X Series, and Virtual Appliances, this step has already been done.
- 2) Upgrade any additional Web Security server components, including transparent identification agents and Remote Filtering Server, that may be running on other machines.
- 3) Upgrade supplemental servers, protectors, mobile agents, and other Forcepoint DLP agents, including Data Security components on ISA and TMG servers.
- 4) Upgrade client components, including the logon application (LogonApp.exe), Remote Filtering Client, Forcepoint Web Security Endpoint and Forcepoint DLP Endpoint.

These actions can be done in parallel. For more information, see the following upgrade guides:

- [Upgrade Guide: Forcepoint Web Security](#)
- [Upgrade Instructions for Forcepoint DLP](#)

